

myCobot API

Before using the following function interfaces, import our API library first. Otherwise it is impossible to run successfully. To download and import the library, refer to 9.2 Compiling and Running of a MycobotCpp Case.

1 Preconditions for controlling the robot arm

1.1 MyCobot(string port, int baud=115200)

Function: to instantiate MyCobot

Return value: none

Parameter description: Parameter 1: serial port number ("COM*" on Windows (such as COM30)

Parameter 2: baud rate (default 115200)

Note: If you want to call the following API, you need to instantiate it first

1.2 Open()

Function: to open the serial port

Return value: none

Parameter description: none

Note: for communication with the robot arm, the serial port should be opened first

1.3 Close()

Function: to close the serial port

Return value: none

Parameter description: none

Note: When the program ends, it is better to close the serial port

2 Overall running status of Robot

2.1 PowerOn()

Function: to power up the robot arm

Return value: none

Parameter description: none

Note: After the robot arm is powered up, it cannot be moved manually

2.2 PowerOff()

Function: to cut off the power for the robot arm

Return value: none

parameter description: none

Note: After the robot arm is powered up, if you want to move it manually, you may use this api to cut off the power of the robot arm

3 MDI program control mode

3.1 SendOneAngle(int jointNo, int angle, int speed)

Function: to send single joint angle

Return value: none

Parameter description: Parameter 1: joint number (1 - 6); Parameter 2: angle (ranging from -170° to 170°); Parameter 3: speed (0-100)

3.2 GetAngles()

Function: to get the angles of all joints

Return value: return an array of int type, int[], length: 6

Description of parameters: none

3.3 SendAngles(int[] angles, int speed)

Function: to send the angles of all joints

Return value: none

Parameter description: Parameter 1: the angles of all joints (ranging from -170° to 170°);

Parameter 2: speed (0-100)

3.4 GetCoords()

Function: to get all coordinates

Return value: return an array of int type, int[], length: 6

Description of parameters: none

3.5 SendCoords(int[] coords, int speed, int mode)

Function: to send multi-parameter coordinates

Return value: none

Parameter description: Parameter 1: All coordinates (The values of X, Y and Z range from -300 to 300.00mm; the values of RX, RY and RZ range from -180 to 180); Parameter 2: speed (0-100);

Parameter 3: mode (0 - angular, and 1 - linear)

3.6 SendOneCoord(int coord, int value, int speed)

Function: to send single parameter coordinates

Return value: none

Parameter description: Parameter 1: coordinate number (1-6(x, y, z, rx, ry, rz)); Parameter 2: coordinate (The values of X, Y and Z range from -300 to 300.00mm; the values of RX, RY and RZ range from -180 to 180); Parameter 3: speed (0-100)

4 Atom end IO control

4.1 SetDigitalOut(byte pin_number, byte pin_signal)

Function: to set the high and low levels of output io

Return value: none

Parameter description: Parameter 1: pin number (atom output pin number), and Parameter 2: state (0-low level, and 1-high level)

4.2 GetDigitalIn(byte pin_number)

Function: to get the state of input io

Return value: pin state (0-low level, and 1-high level)

Parameter description: pin number (atom input pin number)

4.3 setGripperValue(byte angle, byte speed)

Function: to control the adaptive gripper

Return value: none

Parameter description: Parameter 1: gripper opening and closing angles (ranging from 0 to 100; 0-closed; 100-maximum open angle); Parameter 2: gripper opening and closing speeds (0-100)

4.4 SetElectricGriper(byte open)

Function: to control the electric gripper

Return value: none

Parameter description: gripper switch state (0-off, and 1-on)

4.5 getGripperValue()

Function: to get the angle of the adaptive gripper

Return value: int type, return gripper angle (0 - closed; 100 - maximum open angle)

Parameter description: none

5 Stand M5Stack-basic IO control

5.1 SetBasicOut(byte pin_number, byte pin_signal)

Function: to set the high and low levels of output io

Return value: none

Parameter description: Parameter 1: pin number (atom output pin number), and Parameter 2: state (0-low level, and 1-high level)

5.2 GetBasicIn(byte pin_number)

Function: to get state of input io

Return value: pin state (0-low level, and 1-high level)

Parameter description: pin number (basic input pin number)