

myCobot

This is javascript API for mycobot.

MyCobot

Import to your project:

```
// basic demo
var mycobot = require("mycobot")

// obj Based on SerialPort
var obj = mycobot.connect("COM15", 115200)

obj.write(mycobot.powerOn())

// Receive returned data
// obj.on("data", (data)=>{
//     res = mycobot.processReceived(data)
//     console.log("res:", res)
// })
```

Overall status

connect

- **Prototype:** `connect(port, baud)`
- **Description:** Create objects, connect devices (default open).

powerOn

- **Prototype:** `powerOn()`
- **Description:** Atom open communication (default open).

powerOff

- **Prototype:** `powerOff()`
- **Description:** Atom turn off communication.

isPowerOn

- **Prototype:** `isPowerOn()`
- **Description:** Adjust robot arm whether power on.
- **Returns**
 - 1: power on
 - 0: power off

releaseAllServos

- **Prototype:** `releaseAllServos()`
- **Description:** Set robot arm into free moving mode.

MDI mode and operation

getAngles

- **Prototype:** `getAngles()`
- **Description:** Get the degree of all joints.
- **Returns:** `object`: A float list of all degree.

sendAngle

- **Prototype:** `sendAngle(id, degree, speed)`
- **Description:** Send one degree of joint to robot arm.
- **Parameters**
 - `id`: Joint id
 - `degree`: degree value(`number`)
 - `speed`: (`number`) 0 ~ 100
- **Example**

```
obj.write(mycobot.sendAngle(1,50,50))
```

sendAngles()

- **Prototype:** `sendAngles(angles, speed)`
- **Description:** Send the degrees of all joints to robot arm.
- **Parameters**
 - `degrees`: a list of degree value(`Array`).
 - `speed`: (`number`) 0 ~ 100
- **Example**

```
obj.write(mycobot.sendAngles([0,0,0,0,0,0],60))
```

getCoords

- **Prototype:** `getCoords()`
- **Description:** Get the Coords from robot arm, coordinate system based on base.
- **Returns:** `object`: A float list of coord - `mycobot`: [x, y, z, rx, ry, rz]; `mypalletizer`: [x, y, z, θ]

sendCoord

- **Prototype:** `sendCoord(id, coord, speed)`
- **Description:** Send one coord to robot arm.
- **Parameters**
 - `id`: coord id
 - `coord`: coord value(`number`)
 - `speed`: (`number`) 0 ~ 100
- **Example**

```
obj.write(mycobot.sendCoord(x,20,50))
```

sendCoords

- **Prototype:** `sendCoords(coords, speed, mode)`
- **Description:** Send all coords to robot arm.
- **Parameters**
 - `coords`: a list of coords value(`Array`).
 - `speed`: (`number`) 0 ~ 100
 - `mode`: `0` - angular, `1` - linear
- **Example**

```
obj.write(mycobot.sendCoords([160, 160, 160, 0, 0, 0], 70, 0))
```

isInPosition

- **Prototype:** `isInPosition(data, flag)`
- **Description:** Judge whether in the position.
- **Parameters**
 - `data`: A data list, angles or coords.
 - `flag`: Tag the data type, `0` - angles, `1` - coords.
- **Returns**
 - `1` - true
 - `0` - false

JOG mode and operation

jogAngle

- **Prototype:** `jogAngle(jointId, direction, speed)`
- **Description:** Jog control angle
- **Parameters**
 - `jointId`: (`int`) 1 ~ 6
 - `direction`: `0` - decrease, `1` - increase
 - `speed`: 0 ~ 100

jogCoord

- **Prototype:** `jogCoord(coordId, direction, speed)`
- **Description:** Jog control coord.
- **Parameters**
 - `coordId`: (int) 1 ~ 6
 - `direction`: 0 - decrease, 1 - increase
 - `speed`: 0 ~ 100

jogStop

- **Prototype:** `jogStop()`
- **Description:** Stop jog moving.

programPause

- **Prototype:** `programPause()`
- **Description:** Pause movement.

programResume

- **Prototype:** `programResume()`
- **Description:** Recovery movement.

stop

- **Prototype:** `stop()`
- **Description:** Stop moving.

setEncoder

- **Prototype:** `setEncoder(jointId, encoder)`
- **Description:** Set a single joint rotation to the specified potential value.
- **Parameters**
 - `jointId`: 1 ~ 6
 - `encoder`: 0 ~ 4096

getEncoder

- **Prototype:** `getEncoder(jointId)`
- **Description:** Obtain the specified joint potential value.
- **Parameters:** `jointId`: 1 ~ 6
- **Returns:** `encoder`: 0 ~ 4096

setEncoders

- **Prototype:** `setEncoders(encoders, speed)`
- **Description:** Set the six joints of the manipulator to execute synchronously to the specified position.
- **Parameters:**

- `encoders`: A encoder list, length 6.
- `speed`: 0 - 100

getEncoders

- **Prototype:** `getEncoders()`
- **Description:** Get the all joints of the manipulator.
- **Returns:** the list of encoder (`Array`)

Running status and Settings

getSpeed

- **Prototype:** `getSpeed()`
- **Description:** Get speed.
- **Returns:** speed

setSpeed

- **Prototype:** `setSpeed(speed)`
- **Description:** Set speed.
- **Parameters:** speed: 0 ~ 100

getJointMin

- **Prototype:** `getJointMin(jointId)`
- **Description:** Gets the minimum movement angle of the specified joint
- **Parameters:** `jointId`
- **Returns:** angle value (`float`)

getJointMax

- **Prototype:** `getJointMax(jointId)`
- **Description:** Gets the maximum movement angle of the specified joint
- **Parameters:** `jointId`
- **Returns:** angle value (`float`)

Servo control

isServoEnable

- **Prototype:** `isServoEnable(servoId)`
- **Description:** Determine whether all steering gears are connected
- **Parameters:** `servoId` 1 ~ 6
- **Returns**
 - `0`: disable
 - `1`: enable

isAllServoEnable

- **Prototype:** `isAllServoEnable()`
- **Description:** Determine whether the specified steering gear is connected
- **Returns**
 - `0`: disable
 - `1`: enable

setServoData

- **Prototype:** `setServoData(servo_no, dataId, value)`
- **Description:** Set the data parameters of the specified address of the steering gear.
- **Parameters:**
 - `servo_no`: Serial number of articulated steering gear, 1 - 6.
 - `dataId`: Data address.
 - `value`: 0 - 4096

getServodata

- **Prototype:** `getServodata(servo_no, dataId)`
- **Description:** Read the data parameter of the specified address of the steering gear.
- **Parameters:**
 - `servo_no`: Serial number of articulated steering gear, 1 - 6.
 - `dataId`: Data address.
- **Returns:** `value`: 0 - 4096
 - `0`: disable
 - `1`: enable
 - `-1`: error

setServoCalibration

- **Prototype:** `setServoCalibration(servo_no)`
- **Description:** The current position of the calibration joint actuator is the angle zero point, and the corresponding potential value is 2048.
- **Parameters:**
 - `servo_no`: Serial number of articulated steering gear, 1 - 6.

releaseServo

- **Prototype:** `releaseServo(servoId)`
- **Description:** Power off designated servo
- **Parameters:** `servoId`: 1 ~ 6

focusServo

- **Prototype:** `focusServo(servoId)`
- **Description:** Power on designated servo
- **Parameters:** `servoId`: 1 ~ 6

Atom IO

setColor

- **Prototype:** `setColor(r, g, b)`
- **Description:** Set the color of the light on the top of the robot arm.
- **Parameters**
 - `r`: 0 ~ 255
 - `g`: 0 ~ 255
 - `b`: 0 ~ 255

setPinMode

- **Prototype:** `setPinMode(pin_no, pinMode)`
- **Description:** Set the state mode of the specified pin in atom.
- **Parameters**
 - `pin_no` : Pin number.
 - `pinMode` : 0 - input, 1 - output, 2 - inputPullup

setDigitalOutput()

- **Parameters**
 - `pin_no` :
 - `pinSignal` : 0 / 1

getDigitalInput()

- **Parameters:** `pin_no`
- **Return:** signal value

getGripperValue

- **Prototype:** `getGripperValue()`
- **Description:** Get gripper value
- **Return:** gripper value

setGripperState

- **Prototype:** `setGripperState(flag, speed)`
- **Description:** Set gripper switch state
- **Parameters**
 - `flag` : 0 - open, 1 - close

- `speed` : 0 ~ 100

setGripperValue

- **Prototype:** `setGripperValue(value, speed)`
- **Description:** Set gripper value
- **Parameters**
 - `value` : 0 ~ 100
 - `speed` : 0 ~ 100

setGripperIni

- **Prototype:** `setGripperIni()`
- **Description:** Set the current position to zero, set current position value is `2048`.

isGripperMving

- **Prototype:** `isGripperMving()`
- **Description:** Judge whether the gripper is moving or not
- **Returns**
 - `0` : not moving
 - `1` : is moving

M5Stack-basic

setBasicOutput

- **Prototype:** `setBasicOutput(pin_no, pinSignal)`
- **Description:** Set bottom pin.
- **Parameters**
 - `pin_no` : Pin number.
 - `pinSignal` : 0 / 1

getBasicOutput

- **Prototype:** `getBasicOutput(pin_no)`
- **Description:** get bottom pin.
- **Parameters**
 - `pin_no` : Pin number.