

Use cases

In this case, first get the current angles of all joints, then make the joint 1 returns to zero point, and finally get the values of two input pins on M5Stack-basic. The program.cs in the project is a complete use case program, which can be modified as needed on this basis:

```
using System;
using System.Threading;

namespace Mycobot.csharp
{
    class Test
    {
        static void Main(string[] args)
        {
            MyCobot mc = new MyCobot("COM57");
            mc.Open();
            Thread.Sleep(5000);
            // int[] angles = new[] {100, 100, 100, 100, 100, 100};
            // mc.SendAngles(angles, 50);
            var recv = mc.GetAngles();
            foreach (var v in recv)
            {
                Console.WriteLine(v);
            }

            // int[] coords = new[] {160, 160, 160, 0, 0, 0};
            // mc.SendCoords(coords, 90, 1);
            // Thread.Sleep(5000);
            // var recv = mc.GetCoords();
            // foreach (var v in recv)
            // {
            //     Console.WriteLine(v);
            // }

            mc.SendOneAngle(1,0, 70);
            Thread.Sleep(100);
            /*var angle = new int[6];
            angle = mc.GetAngles();
            foreach (var v in angle)
                Console.WriteLine(v);
            // byte[] setColor = {0xfe, 0xfe, 0x05, 0x6a, 0xff, 0x00, 0x00,
0xfa}*/

            //set basic output io
            /*mc.SetBasicOut(2, 1);
            Thread.Sleep(100);
            mc.SetBasicOut(5, 1);
            Thread.Sleep(100);
            mc.SetBasicOut(26, 1);
            Thread.Sleep(100);*/
```

```

        //get basic input io
        Console.WriteLine(mc.GetBasicIn(35));
        Thread.Sleep(100);
        Console.WriteLine(mc.GetBasicIn(36));
        Thread.Sleep(100);

        //set atom output io
        /*mc.SetDigitalOut(23, 0);
        Thread.Sleep(100);
        mc.SetDigitalOut(33, 0);
        Thread.Sleep(100);*/

        //get m5 input io
        /*Console.WriteLine(mc.GetDigitalIn(19));
        Thread.Sleep(100);
        Console.WriteLine(mc.GetDigitalIn(22));
        Thread.Sleep(100);*/

        //set gripper open or close 0--close 100--open max 0-100
        /*mc.setGripperValue(0, 10);
        Thread.Sleep(3000);
        mc.setGripperValue(50, 100);
        Thread.Sleep(3000);*/

        //get gripper state 0--close 1--open
        /*Console.WriteLine(mc.getGripperValue());*/
        mc.Close();
    }
}
}

```